

Knowledgebase > SalesPad > Sales > FedEx Address Validation

FedEx Address Validation

Megan De Freitas - 2025-06-16 - Sales


Overview

FedEx Address Validation adds the ability to validate addresses through FedEx's API. Addresses are validated on the Customer Address card and the Ship To Address on a sales document.

Note: This functionality requires an additional dll to use. Please contact <u>SalesPad Support</u> to request the dll for your build of SalesPad.

Settings Setup

- 1. Navigate to Settings and locate the Address Tools section.
- 2. Select FedExAddressQueryHandler from the list of Address Query Handlers.




- 4. Fill out each field with the appropriate FedEx credentials.
- 5. Click **Save.**

Usage

Customer Address card


 $1. \ \ Navigate\ to\ a\ Customer\ Address\ card.$



2. Input the desired information and click **Save.** The address will be validated upon the save.

Sales Document Addresses Tab

- 1. Navigate to the Addresses Tab on a new or open sales document.
- 2. If needed, the update the Ship To Address.



3. Save the sales document. The Ship To Address will be validated upon the save.

Settings

Address Query Handlers - Specify the Address Query Handler to be used. This item has no default value.

Note: This must be set to FedEx Query Handler to use FedEx address validation. Without the FedEx Address Validation dll, this option will not be available.

DPV Shipping Method - DPV (Delivery Point Validation) indicates that an address can receive mail. When this setting is filled in, an address that has a valid DPV will have this shipping method set. This item has no default value.

FedEx Meter Number - FedEx user meter number used for authorization. This item has no default value.

FedEx User Account Number - FedEx user account number used for authorization. This item has no default value.

FedEx User Credential Key - FedEx user credential key used for authorization. This item has no default value.

 $FedEx\ User\ Credential\ Password$ - FedEx user credential password used for authorization. This item has no default value.

Post Address Validation Script - C# script that fires after an address has been validated. This item has no default value. Parameters: CustomerAddr Customer Address, SalesPad.Bus.SalesDocument sd, SalesPad.Module.FedExAddressVAlidation.WebReference.AddressValidationReply response

Validation Precision - Determines how precise the address validation should be. Exact means the entire address needs to be matched by FedEx, Medium means it will validate the street/city combination but not necessarily the house number. Defaults to Medium.