



## FedEx Address Validation



Megan De Freitas - 2024-12-03 - Sales

### Overview

FedEx Address Validation adds the ability to validate addresses through FedEx's API. Addresses are validated on the Customer Address card and the Ship To Address on a sales document.


**Note:** This functionality requires an additional dll to use. Please contact [SalesPad Support](#) to request the dll for your build of SalesPad.

### Settings Setup


1. Navigate to Settings and locate the Address Tools section.
2. Select FedExAddressQueryHandler from the list of *Address Query Handlers*.
3. Locate the *FedEx Validation* section under settings.
4. Fill out each field with the appropriate FedEx credentials.
5. Click **Save**.

### Usage

#### Customer Address card

1. Navigate to a Customer Address card.
2. Input the desired information and click **Save**. The address will be validated upon the save.

#### Sales Document Addresses Tab

1. Navigate to the Addresses Tab on a new or open sales document.
2. If needed, the update the Ship To Address.
3. Save the sales document. The Ship To Address will be validated upon the save.

### Settings

*Address Query Handlers* - Specify the Address Query Handler to be used. This item has no default value.

**Note:** This must be set to FedEx Query Handler to use FedEx address validation. Without the FedEx Address Validation dll, this option will not be available.

*DPV Shipping Method* - DPV (Delivery Point Validation) indicates that an address can receive mail. When this setting is filled in, an address that has a valid DPV will have this shipping method set. This item has no default value.

*FedEx Meter Number* - FedEx user meter number used for authorization. This item has no default value.

*FedEx User Account Number* - FedEx user account number used for authorization. This item has no default value.

*FedEx User Credential Key* - FedEx user credential key used for authorization. This item has no default value.

*FedEx User Credential Password* - FedEx user credential password used for authorization. This item has no default value.

*Post Address Validation Script* - C# script that fires after an address has been validated. This item has no default value. Parameters: CustomerAddr Customer Address, SalesPad.Bus.SalesDocument sd, SalesPad.Module.FedExAddressValidation.WebReference.AddressValidationReply response

*Validation Precision* - Determines how precise the address validation should be. Exact means the entire address needs to be matched by FedEx, Medium means it will validate the street/city combination but not necessarily the house number. Defaults to Medium.