

Knowledgebase > ShipCenter > Miscellaneous > ShipCenter Supported Scales

ShipCenter Supported Scales

Megan De Freitas - 2024-12-03 - Miscellaneous

Overview

ShipCenter supports multiple scale brands for weighing shipments. ShipCenter supports any USB scale using the HID POS protocol. USB scales from Mettler Toledo, Dymo, and Fairbanks require no additional configuration and can be considered "plug and play."

Using a Scale in ShipCenter

From a new shipment, a scale can be used to update the Weight field. To calculate the weight, place the shipment on a connected scale and click the **Enable USB Scale** button.

	PENDING SHIPMENT	
Weight		
Weight	0	÷.
Weight UofM	LBS	~

The weight of the package as recorded on the scale will populate in the weight field.

Using a Scale with Multi-Package Shipments

For shipments with more than one package, the following process must be followed:

- 1. With the scale enabled, place the package on the scale.
- After the weight has stabilized and you are ready to weigh the next package, click Next. This will capture the weight of the first package.

1 of 1 Packages								
Items	\bigotimes	Delete		Previous	Next	\Rightarrow	Finish Shipment	
🗛 Notes								

- 3. Remove the previous package from the scale, and place the next package on the scale.
- 4. Repeat steps 2 & 3 until all packages have been weighed.
- 5. When finished weighing the packages, or if changes are needed on a previous package, stop the scale by clicking on the **Enable USB Scale** button. Failure to do so will result in package weights being overwritten.

Settings

Automatically Start Weight Scale - If set to True, the weight scale will be automatically

enabled when opening a Shipment. Defaults to False.

Weight Scale - Determines the scale used while the Weight Scale button is enabled on the Shipment Editor. If blank, ShipCenter will attempt to automatically detect a Dymo, Mettler Toledo, or Stamps.com scale. Defaults to n/a.

VID/PID numbers can be located in the Windows Device Manager properties.

Application Settings ×						
Close 🚽 Save						
scale						
21 2						
✓ Weight Scale	✓ Weight Scale					
Automatically Start Weight Scale	False					
Weight Scale						
	VID_2516&PID_0055:Usbhid VID_047F&PID_AC01:Usbhid VID_1532&PID_0501:Usbhid VID_046D&PID_C245:Usbhid					